

# Input Instructions for RECONR

```
*****
*
* card 1
*   nendf    unit for endf/b tape
*   npend    unit for pendf tape
* card 2
*   tlabel   66 character label for new pendf tape
*             delimited with quotes, ended with /.
* card 3
*   mat      material to be reconstructed
*   ncards   number of cards of descriptive data for new mf1
*             (default=0.)
*   ngrid    number of user energy grid points to be added.
*             (default=0.)
* card 4
*   err      fractional reconstruction tolerance used when
*             resonance-integral error criterion (see errint)
*             is not satisfied.
*   tempr    reconstruction temperature (deg kelvin)
*             (default=0.)
*   errmax   fractional reconstruction tolerance used when
*             resonance-integral error criterion is satisfied
*             (errmax.ge.err, default=20.*err)
*   errint   maximum resonance-integral error (in barns)
*             per grid point (default=err/10000)
*             (note: the max cross section difference for
*             linearization, errlim, and for reconstruction,
*             errmin, are also tied to errint.  to get maximum
*             accuracy, set errint to a very small number.
*             for economical production, use the defaults.)
* card 5
*   cards    ncards of descriptive comments for mt451
*             each card delimited with quotes, ended with /.
* card 6
*   enode    users energy grid points
*
*   cards 3, 4, 5, 6 must be input for each material desired
*   mat=0/ terminates execution of reconr.
*
*****
```